

WOF

v1.16

Generated by Doxygen 1.9.1

1 Main Page	1
2 Module Index	4
2.1 Modules	4
3 Namespace Index	4
3.1 Namespace List	4
4 Hierarchical Index	4
4.1 Class Hierarchy	4
5 Class Index	5
5.1 Class List	5
6 File Index	5
6.1 File List	5
7 Module Documentation	5
7.1 License related functions	5
7.1.1 Detailed Description	6
7.1.2 Macro Definition Documentation	6
7.1.3 Function Documentation	6
7.2 Version related functions	7
7.2.1 Detailed Description	8
7.2.2 Function Documentation	8
7.3 Geometry functions	8
7.3.1 Detailed Description	9
7.3.2 Function Documentation	9
7.4 File I/O	11
7.4.1 Detailed Description	12
7.4.2 Enumeration Type Documentation	12
7.4.3 Function Documentation	12
8 Namespace Documentation	16
8.1 GEOM_WOF Namespace Reference	16
8.1.1 Detailed Description	18
8.1.2 Typedef Documentation	18
8.1.3 Function Documentation	18
9 Class Documentation	19
9.1 GEOM_WOF::Mesh Class Reference	19
9.1.1 Detailed Description	19
9.1.2 Member Function Documentation	19
9.2 GEOM_WOF::Point3 Class Reference	21
9.2.1 Constructor & Destructor Documentation	23

9.2.2 Member Function Documentation	24
9.3 GEOM_WOF::ProgressBase Class Reference	28
9.3.1 Detailed Description	28
9.3.2 Member Function Documentation	28
9.4 GEOM_WOF::TimerC Class Reference	28
9.4.1 Detailed Description	29
9.4.2 Constructor & Destructor Documentation	29
9.4.3 Member Function Documentation	29
9.5 GEOM_WOF::Vector3 Class Reference	29
9.5.1 Constructor & Destructor Documentation	31
9.5.2 Member Function Documentation	31
9.6 GEOM_WOF::WofBugException Struct Reference	33
9.6.1 Detailed Description	34
9.7 GEOM_WOF::WofLicenseException Class Reference	34
9.7.1 Detailed Description	34
10 File Documentation	34
10.1 wof_api.h File Reference	34
10.2 wof_api_definitions.h File Reference	35
10.3 wof_api_functions.h File Reference	35
10.4 wof_api_io.h File Reference	36
Index	39

1 Main Page

WOF C++ Point Cloud Mesher

- **Point cloud to mesh** - Fast surface reconstruction software
- **Mesh to point cloud** - Quality point cloud creator
- **Mesh to mesh** - Convert a mesh into a point cloud and reconstruct it from there

WOF is as a **C++ library and command line executable** for Windows and Linux development.

Download the WOF library and command line application

There are two WOF builds:

- **WOF PURE** comes without any dependencies so it can be integrated smoothly. It includes a 500 000 points student/eval license.
- **WOF LM** comes with a license manager (LM) and allows an unlimited number of points during the trial period.

Both variants contain a dynamic C++ library, a command line application, C++ examples and documentation.

License

WOF is a commercial project with maintenance and support.

- A free **student license** for non-commercial research and evaluation is included in the PURE build. It allows 500 000 points.
 - The LM build includes an **evaluation license** for research and commercial tests. It is unlimited during the trial period. If you want to use WOF in your commercial project, please contact the author and give as much information as possible.
-

Release Notes and Version History

Version 1.16, December 7th, 2023:

- Bugfix in estimateAvgSpacing()
- Default for `-numGrowSteps` in wof.exe adapted to 1

Version 1.15, December 6th, 2023:

- Hole closing improved

Version 1.14, August 24th, 2023:

- Algorithms optimized, WOF is much faster now
- Memory leak fixed.
- Better quality

Version 1.13, January 18th, 2023:

- Support for RGB color
- Memory leak fixed
- Performance improved

Version 1.12, Sep 29th, 2022:

- New hole closing algorithm, use the `-H` option
- Stability improved

Version 1.11, May 23rd, 2022:

- Bugfix when no work in progress bar
- New function `estimateAvgSpacing()` to estimate the density of a point cloud

Version 1.10, May 7th, 2022:

- Progress bar support
- Two separate variants: PURE and LM
- Extended API for detailed control over mesh reduction, mesh smoothing and edge flips.

- C++ example improved

Version 1.09, March 16th, 2022:

- Laplacian smoothing removes noise
- Edge flips fit the triangulation to the thought surface
- Mesh simplification reduces the number of triangles
- Better performance
- Multithreading improved
- Bugfixes
- Enhanced C++-API

Version 1.08, February 17th, 2022:

- Another bugfix

Version 1.07, February 16th, 2022:

- Bugfix in yesterday's version

Version 1.06, February 15th, 2022:

- Mesh melting improved.
- Tiny holes due to poor sampling are better avoided.
- Bugs solved.
- Quality improved.

Version 1.05, July 6th, 2021:

- Improved mesh melting

Version 1.04, April 3rd, 2020:

- Static and dynamic linking is now available (*static linking since v1.10 to reduce the complexity*)
- CMake improved, Visual Studio project, Makefile
- Example data exchanged

Version 1.03, March 23rd, 2020:

First official release of the WOF software:

- Readers and Writers for the *.ply, *.stl, *.asc, *.bin, *.list file formats exist now
- A Mesh-to-Cloud method has been added
- An API has been made
- The library has been tested for memory leaks
- Documentation pages have been written

Version Beta2, October 2019

- Reconstruction quality improved
- Library versions added

Version Beta1, March 2019

- This software is developed since 2016 when it was a module of the Fade2D software.
- For flexibility reasons the whole point cloud topic has been moved to the separate WOF project now.

2 Module Index

2.1 Modules

Here is a list of all modules:

License related functions	5
Version related functions	7
Geometry functions	8
File I/O	11

3 Namespace Index

3.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

GEOM_WOF	16
-----------------	-----------

4 Hierarchical Index

4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

std::exception

GEOM_WOF::WofBugException	33
GEOM_WOF::WofLicenseException	34
GEOM_WOF::Mesh	19
GEOM_WOF::Point3	21
GEOM_WOF::ProgressBase	28
GEOM_WOF::TimerC	28
GEOM_WOF::Vector3	29

5 Class Index

5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

GEOM_WOF::Mesh	
3D Mesh class	19
GEOM_WOF::Point3	
3D Point	21
GEOM_WOF::ProgressBase	
Base class for progress subscribers	28
GEOM_WOF::TimerC	
Timer class	28
GEOM_WOF::Vector3	
3D Vector	29
GEOM_WOF::WofBugException	
Bug-Exception	33
GEOM_WOF::WofLicenseException	
License-Exception	34

6 File Index

6.1 File List

Here is a list of all documented files with brief descriptions:

Mesh.h	??
Point3.h	??
TimerC.h	??
Vector3.h	??
wof_api.h	34
wof_api_definitions.h	35
wof_api_functions.h	35
wof_api_io.h	36

7 Module Documentation

7.1 License related functions

License related functions for "LM" builds.

Macros

- `#define WOFLIC_ACTIVATED` 10
- `#define WOFLIC_GRACE_OK` 11
- `#define WOFLIC_GRACE_EXPIRED` 12

- `#define WOFLIC_TRIAL 13`
- `#define WOFLIC_INVALID 14`
- `#define WOFLIC_PURE 15`

Functions

- `int GEOM_WOF::getLicenseState ()`
Check the license state.
- `void GEOM_WOF::printLicense ()`
Print license details.
- `bool GEOM_WOF::isPure ()`
Check if pure or lm build.
- `bool GEOM_WOF::activateWof (const char *key, bool bSystemWide)`
Activate WOF license.
- `bool GEOM_WOF::deactivateWof ()`
Deactivate WOF license.
- `bool GEOM_WOF::extendTrial (const char *key)`
Extend Trial.

7.1.1 Detailed Description

Functions related to the license: Activation, deactivation, trial-extension... Not active in "PURE" builds.

7.1.2 Macro Definition Documentation

7.1.2.1 WOFLIC_ACTIVATED `#define WOFLIC_ACTIVATED 10`
WOFLIC_ACTIVATED means the software is activated

7.1.2.2 WOFLIC_GRACE_EXPIRED `#define WOFLIC_GRACE_EXPIRED 12`
WOFLIC_GRACE_EXPIRED means the software is activated but re-verification (no internet) has failed for a long time. Invalid.

7.1.2.3 WOFLIC_GRACE_OK `#define WOFLIC_GRACE_OK 11`
WOFLIC_GRACE_OK means the software is activated but re-verification has failed (no internet, valid for a sufficiently long grace period)

7.1.2.4 WOFLIC_INVALID `#define WOFLIC_INVALID 14`
WOFLIC_INVALID means there is no valid license (trial, product-key)

7.1.2.5 WOFLIC_PURE `#define WOFLIC_PURE 15`
WOFLIC_PURE is the perpetual non-commercial license

7.1.2.6 WOFLIC_TRIAL `#define WOFLIC_TRIAL 13`
WOFLIC_TRIAL means the trial period is still active

7.1.3 Function Documentation

7.1.3.1 activateWof() `bool GEOM_WOF::activateWof (`
`const char * key,`
`bool bSystemWide)`

This function is used when you have a WOF license key. You can choose to activate system-wide or only for the current user.

Parameters

<i>key</i>	is the purchased software key
<i>bSystemWide</i>	When true then the activation data is stored system-wide. When false the activation is made for the current user.

Note

Activation is only done once. You can use [getLicenseState\(\)](#) to find out if the software is already activated.

When the system-wide activation is chosen (`bSystemWide=true`) then the application needs admin-privileges.

7.1.3.2 deactivateWof() `bool GEOM_WOF::deactivateWof ()`

Deactivates the WOF license on the present computer so that the key can be used on another machine. This function enables you to replace a computer. Do not use over-frequently, the number of deactivations is limited, it's not a floating license.

Returns

true in case of success, false otherwise

7.1.3.3 extendTrial() `bool GEOM_WOF::extendTrial (`
`const char * key)`

Parameters

<i>key</i>	is a Trial-Extension-key. You ask for such a key to extend the trial period for your non-commercial research project (see the guidelines) or for an extended commercial test period.
------------	--

Returns

true in case of success, false otherwise

7.1.3.4 getLicenseState() `int GEOM_WOF::getLicenseState ()`

Returns

[WOFLIC_ACTIVATED](#) when the software is activated

[WOFLIC_TRIAL](#) during the trial period

[WOFLIC_GRACE_OK](#) when activated but verification has failed (no internet access) which is valid for a grace period

[WOFLIC_GRACE_EXPIRED](#) when activated but verification has failed (no internet) for a long time

[WOFLIC_INVALID](#) otherwise (trial expired, no license)

7.2 Version related functions

Version related functions.

Functions

- void [GEOM_WOF::printVersion](#) ()
Print version number.

- void `GEOM_WOF::getVersion` (int &versionMajor, int &versionMinor)
Get version numbers.
- bool `GEOM_WOF::isRelease` ()
Check if the present binary is a Release or Debug build.

7.2.1 Detailed Description

Functions to identify Debug- and Release builds and to fetch the version number.

7.2.2 Function Documentation

7.2.2.1 `getVersion()` void `GEOM_WOF::getVersion` (
int & *versionMajor*,
int & *versionMinor*)

Returns the WOF version number

Parameters

<i>versionMajor, versionMinor</i>	[out] are used to return the major and minor version number
-----------------------------------	---

7.2.2.2 `isRelease()` bool `GEOM_WOF::isRelease` ()

Returns

true when the library has been compiled in release mode or false otherwise

7.2.2.3 `printVersion()` void `GEOM_WOF::printVersion` ()

Prints the version number to stdout

7.3 Geometry functions

Geometry operations.

Functions

- `MeshPtr GEOM_WOF::melt` (std::vector< `Point3` > &vInputCorners, double avgLength, double featureThresh=15.0)
Remesh (melt) a triangle mesh.
- `MeshPtr GEOM_WOF::reconstruct_auto` (std::vector< `Point3` > &vPoints, double sfactor=2.0, int numGrowSteps=10)
Reconstruct with an automatic spacing value.
- `MeshPtr GEOM_WOF::reconstruct_abs` (std::vector< `Point3` > &vPoints, double spacingAbs, int numGrowSteps=10)
Reconstruct with an absolute spacing value.
- void `GEOM_WOF::toCloud` (std::vector< `Point3` > &vCornersIn, double length, double featureThresh, std::vector< `Point3` > &vCloudOut)
Mesh-to-Cloud.
- void `GEOM_WOF::edgeFlips` (`MeshPtr` pMesh)
Flip edges.
- void `GEOM_WOF::edgeFlipsSimA` (`MeshPtr` pMesh)
Flip edges - simulated annealing.

- void [GEOM_WOF::laplacianSmoothing](#) ([MeshPtr](#) pMesh, int numIterations)
Laplacian smoothing.
- int [GEOM_WOF::reduce](#) ([MeshPtr](#) pMesh, double targetLen=DBL_MAX, double maxDev=2.0)
Reduce.

7.3.1 Detailed Description

Operations to reconstruct a surface, to sample-and-reconstruct a mesh and to create feature-aligned quality point clouds.

7.3.2 Function Documentation

7.3.2.1 [edgeFlips\(\)](#) void [GEOM_WOF::edgeFlips](#) (
[MeshPtr](#) pMesh)

This function uses a simple and fast edge-flip algorithm to fit the mesh better to thought surface.

Parameters

in	pMesh	is the mesh to be improved
----	-----------------------	----------------------------

See also

[edgeFlipsSimA\(\)](#)

7.3.2.2 [edgeFlipsSimA\(\)](#) void [GEOM_WOF::edgeFlipsSimA](#) (
[MeshPtr](#) pMesh)

Like [edgeFlips\(\)](#) the present function flips edges to adapt the mesh better to the thought surface. But with a computationally more expensive simulated annealing algorithm that achieves yet better output quality.

Parameters

in	pMesh	is the mesh to be improved
----	-----------------------	----------------------------

See also

[edgeFlips\(\)](#)

7.3.2.3 [laplacianSmoothing\(\)](#) void [GEOM_WOF::laplacianSmoothing](#) (
[MeshPtr](#) pMesh,
int numIterations)

This function applies weighted laplacian smoothing to create a smoother mesh.

Parameters

in	pMesh	is the mesh to be improved
in	numIterations	specifies how much the mesh shall be smoothed.

7.3.2.4 [melt\(\)](#) [MeshPtr](#) [GEOM_WOF::melt](#) (

```
std::vector< Point3 > & vInputCorners,
double avgLength,
double featureThresh = 15.0 )
```

This function converts a mesh into a point cloud and then reconstructs it from there. This way you can get rid of meshing errors and unnecessary complexity. This mesh-melting operation may change the topology of the object i.e., depending on the sample distance it may close holes and create additional bridges.

Parameters

in	<i>vInputCorners</i>	contains the input triangles (3 corner points per triangle)
in	<i>avgLength</i>	specifies the average distance to be used. Choose this parameter with care to avoid an extreme number of elements.
in	<i>featureThresh</i>	is an optional parameter that specifies that edges above this value shall be treated as feature lines on which points shall be placed.

7.3.2.5 reconstruct_abs() `MeshPtr` GEOM_WOF::reconstruct_abs (

```
std::vector< Point3 > & vPoints,
double spacingAbs,
int numGrowSteps = 10 )
```

This function reconstructs a triangular mesh from a 3D point cloud.

Parameters

in	<i>vPoints</i>	contains the input point cloud
in	<i>spacingAbs</i>	is an absolute spacing value. Large values
in	<i>numGrowSteps</i>	is the number of steps by which the boundaries of holes can grow to close the holes. The steps correspond approximately to the used spacing distance. Larger values close larger holes and can take considerably more time.

Returns

the reconstructed mesh.

If the absolute spacing value is unknown then better use [reconstruct_auto\(\)](#) which automatically estimates the point cloud density.

See also

[reduce\(\)](#), [laplacianSmoothing\(\)](#), [edgeFlips\(\)](#), [edgeFlipsSimA\(\)](#) which are powerful postprocessing fuctions.

7.3.2.6 reconstruct_auto() `MeshPtr` GEOM_WOF::reconstruct_auto (

```
std::vector< Point3 > & vPoints,
double sfactor = 2.0,
int numGrowSteps = 10 )
```

This function reconstructs a triangular mesh from a 3D point cloud.

Parameters

in	<i>vPoints</i>	contains the input point cloud
in	<i>sfactor</i>	is a factor on the estimated point cloud density. The average spacing in the point cloud is automatically estimated and multiplied by sfactor. Use larger values to avoid holes upfront and to create coarser meshes. By default sfactor=2.0.
in	<i>numGrowSteps</i>	is the number of steps by which the boundaries of holes can grow to close the holes. The steps correspond approximately to the used spacing distance. Use 0 to deactivate. Larger values close larger holes but also take more time.

Returns

the reconstructed mesh.

See also

[reduce\(\)](#), [laplacianSmoothing\(\)](#), [edgeFlips\(\)](#), [edgeFlipsSimA\(\)](#) which are powerful postprocessing fuctions.

7.3.2.7 reduce() `int GEOM_WOF::reduce (`
`MeshPtr pMesh,`
`double targetLen = DBL_MAX,`
`double maxDev = 2.0)`

This function reduces the number of triangles in `pMesh`.

Parameters

in	<i>pMesh</i>	is the mesh to be simplified
in	<i>targetLen</i>	is a limit on the edge length (the algorithm will skip larger edges). Default: DBL_MAX
in	<i>maximum</i>	angle deviation per simplification step. Default: 2.0

Returns

the number of removed triangles

7.3.2.8 toCloud() `void GEOM_WOF::toCloud (`
`std::vector< Point3 > & vCornersIn,`
`double length,`
`double featureThresh,`
`std::vector< Point3 > & vCloudOut)`

This function creates a 3D point cloud from an input mesh.

Parameters

in	<i>vCornersIn</i>	contains the input triangles (3 corners per triangle)
in	<i>length</i>	specifies the approximate distance to be used
in	<i>featureThresh</i>	is an optional parameter. Edges with larger dihedral angles are treated as feature edges and points are preferably placed there.
out	<i>vCloudOut</i>	is used to return the point cloud

7.4 File I/O

IO functions.

Enumerations

- enum [GEOM_WOF::FileType](#) {
[GEOM_WOF::FT_STL](#) , [GEOM_WOF::FT_PLY](#) , [GEOM_WOF::FT_XYZ](#) , [GEOM_WOF::FT_BIN](#) ,
[GEOM_WOF::FT_LIST](#) , [GEOM_WOF::FT_UNKNOWN](#) }
Filetype.

Functions

- [FileType](#) [GEOM_WOF::getFileTypes](#) (const std::string &filename)

Get File Type.

- bool `GEOM_WOF::writePoints_ASCII` (const char *filename, const std::vector< `Point3` > &vPoints)
Write points to an ASCII file.
- bool `GEOM_WOF::writePoints_BIN` (const char *filename, std::vector< `Point3` > &vPoints)
Write points to a binary file.
- bool `GEOM_WOF::readPly` (const char *filename, bool bReadPoints, std::vector< `Point3` > &vPointsOut)
*Write points to a *.ply file.*
- bool `GEOM_WOF::writePointsPly` (const std::string &filename, std::vector< `GEOM_WOF::Point3` > &vPoints, bool bASCII)
- bool `GEOM_WOF::readPoints_ASCII` (const char *filename, std::vector< `Point3` > &vPoints)
Read points from an ASCII file.
- bool `GEOM_WOF::readPoints_BIN` (const char *filename, std::vector< `Point3` > &vPointsOut)
Read points from a binary file.
- bool `GEOM_WOF::readSTL_ASCII` (const char *filename, std::vector< `Point3` > &vTriangleCorners)
Read a mesh from ASCII STL.
- bool `GEOM_WOF::readPoints_auto` (std::string &inFilename, std::vector< `Point3` > &vPoints)
Read points from a file (automatic detection)
- bool `GEOM_WOF::writePoints_auto` (std::string &outFilename, std::vector< `Point3` > &vPoints, bool bASCII)
Write points to a file.
- bool `GEOM_WOF::writeMesh_auto` (const std::string &filename, std::shared_ptr< `Mesh` > pMesh, bool bASCII)
Write mesh to a file.

7.4.1 Detailed Description

Read/Write functions for point clouds and triangle meshes.

7.4.2 Enumeration Type Documentation

7.4.2.1 FileType `enum GEOM_WOF::FileType`

Enumerator

FT_STL	FileType STL based on the filename extension [.stl].
FT_PLY	FileType PLY based on the filename extension [.ply].
FT_XYZ	FileType XYZ based on the filename extensions [.xyz .txt .asc].
FT_BIN	FileType BIN based on the filename extension [.bin].
FT_LIST	FileType LIST based on the filename extension [.list].
FT_UNKNOWN	FileType UNKNOWN for unknown extensions.

7.4.3 Function Documentation

7.4.3.1 `getFileType()` `FileType GEOM_WOF::getFileType (const std::string & filename)`

Returns

the file type (`FT_STL`, `FT_PLY`, `FT_XYZ`, `FT_BIN`, `FT_LIST`, `FT_UNKNOWN`) based on the filename extension.

7.4.3.2 readPly() `bool GEOM_WOF::readPly (`
`const char * filename,`
`bool bReadPoints,`
`std::vector< Point3 > & vPointsOut)`

Parameters

<i>filename</i>	[in] is the input filename
<i>bReadPoints</i>	[in] Use true to get only the points of the *.ply file. Otherwise, when you are interested in the triangles then use false to get 3 subsequent corners per triangle.
<i>vPointsOut</i>	[out] is used to return the points

Returns

true when the operation was successful or false otherwise

Note

This function reads also colors whose ply properties are named 'red','green','blue' or alternatively 'r','g','b'. Alpha can be named 'alpha' or 'scalar_Intensity'. Values are stored as unsigned char i.e., 0-255 and are automatically scaled up if given in the range 0.0-1.0 or scaled down if >255.0.

7.4.3.3 readPoints_ASCII() `bool GEOM_WOF::readPoints_ASCII (`
`const char * filename,`
`std::vector< Point3 > & vPoints)`

Reads points from a simple ASCII file. Expected file format: Three coordinates (x y z) per line, whitespace separated.

Parameters

<i>filename</i>	[in] is the input filename
<i>vPoints</i>	[out] is used to return the points

Returns

true [in] in case of success or false otherwise

7.4.3.4 readPoints_auto() `bool GEOM_WOF::readPoints_auto (`
`std::string & inFilename,`
`std::vector< Point3 > & vPoints)`

This function reads points from a *.ply-File (ASCII or binary), an *.xyz-File (ASCII, 3 coordinates per line), or a *.bin-File (simple binary format). The file type is automatically determined from the filename extension.

Parameters

in	<i>inFilename</i>	is the input filename
out	<i>vPoints</i>	is used to return the points

Returns

true in case of success, false otherwise

See also

In case of a *.ply file colors are also read, see [readPly\(\)](#) for details on colors.

7.4.3.5 readPoints_BIN() `bool GEOM_WOF::readPoints_BIN (`
`const char * filename,`
`std::vector< Point3 > & vPointsOut)`

Parameters

<i>filename</i>	[in] is a binary input file
<i>vPointsOut</i>	[out] is used to return the points

Returns

true in case of success or false otherwise

See also

[writePoints_BIN\(\)](#)

7.4.3.6 readSTL_ASCII() `bool GEOM_WOF::readSTL_ASCII (`
`const char * filename,`
`std::vector< Point3 > & vTriangleCorners)`

Parameters

<i>filename</i>	[in] is the input filename
<i>vTriangleCorners</i>	[out] is used to return three points per triangle

Returns

true when the operation was successful or false otherwise

7.4.3.7 writeMesh_auto() `bool GEOM_WOF::writeMesh_auto (`
`const std::string & filename,`
`std::shared_ptr< Mesh > pMesh,`
`bool bASCII)`

This function writes a [Mesh](#) to file. Available formats are *.ply (ASCII or binary), *.stl (only ASCII) and Geomview-*.list (ASCII). The file type is automatically determined from the filename extension.

Parameters

in	<i>filename</i>	is the output filename
in	<i>pMesh</i>	is the mesh to be written
in	<i>bASCII</i>	specifies that ASCII mode shall be used when the file can be written in ASCII- or binary mode (as it is the case for *.ply)

Returns

true in case of success or false otherwise

7.4.3.8 writePoints_ASCII() `bool GEOM_WOF::writePoints_ASCII (`
`const char * filename,`
`const std::vector< Point3 > & vPoints)`

Writes points to an ASCII file, three coordinates (x y z) per line, whitespace separated.

Note

Data exchange through ASCII files is easy and convenient but floating point coordinates are not necessarily exact when represented as decimal numbers and ASCII files are big compared to other formats. Thus writing binary files using [writePoints_BIN\(\)](#) is recommended.

Parameters

<i>filename</i>	[in] is the output filename
<i>vPoints</i>	[in] contains the points to be written

Returns

true when the operation was successful or false otherwise.

7.4.3.9 writePoints_auto() `bool GEOM_WOF::writePoints_auto (`
`std::string & outFilename,`
`std::vector< Point3 > & vPoints,`
`bool bASCII)`

This function writes points to a *.ply-File, *.xyz-File (ASCII, 3 coordinates per line), or a *.bin-File (simple binary format). The file type is automatically determined from the filename extension.

Parameters

in	<i>outFilename</i>	is the output filename
in	<i>vPoints</i>	contains the points to be written
in	<i>bASCII</i>	specifies that ASCII mode shall be used when the file can be written in ASCII- or binary mode (as it is the case for *.ply)

Returns

true in case of success or false otherwise

7.4.3.10 writePoints_BIN() `bool GEOM_WOF::writePoints_BIN (`
`const char * filename,`
`std::vector< Point3 > & vPoints)`

Writes a binary file, the format is: (int,size_t,double,...,double)

Thereby the first int is always 30, the size_t value is vPoints.size() and the double precision values are x0,y0,z0,...,xn,yn,zn.

Parameters

in	<i>filename</i>	is the output filename
in	<i>vPoints</i>	contains the points to be written

Returns

true when the operation was successful or false otherwise

See also

[readPoints_BIN\(\)](#)

8 Namespace Documentation

8.1 GEOM_WOF Namespace Reference

Classes

- class [Point3](#)
3D Point
- class [TimerC](#)
Timer class.
- class [Vector3](#)
3D Vector
- class [WofLicenseException](#)
License-Exception.
- struct [WofBugException](#)
Bug-Exception.
- class [ProgressBase](#)
Base class for progress subscribers.
- class [Mesh](#)
3D [Mesh](#) class

Typedefs

- typedef std::shared_ptr< [Mesh](#) > [MeshPtr](#)

Enumerations

- enum [FileType](#) {
 [FT_STL](#) , [FT_PLY](#) , [FT_XYZ](#) , [FT_BIN](#) ,
 [FT_LIST](#) , [FT_UNKNOWN](#) }
Filetype.

Functions

- std::ostream & **operator**<< (std::ostream &stream, const [Point3](#) &pnt)
- std::istream & **operator**>> (std::istream &stream, [Point3](#) &pnt)
- double [sqDistance](#) (const [Point3](#) &p0, const [Point3](#) &p1)
Get the squared distance between two points.
- double [sqDistance](#) (const [Point3](#) *p0, const [Point3](#) *p1)
Get the squared distance between two points.
- double [distance](#) (const [Point3](#) &p0, const [Point3](#) &p1)
Get the squared distance between two points.
- [Point3](#) [center](#) (const [Point3](#) &p0, const [Point3](#) &p1)
Midpoint of p0 and p1.
- std::ostream & **operator**<< (std::ostream &stream, const [Vector3](#) &vec)
- [Vector3](#) [crossProduct](#) (const [Vector3](#) &vec0, const [Vector3](#) &vec1)
Cross product.
- [Vector3](#) [normalize](#) (const [Vector3](#) &other)

- Normalize.*
- **Vector3 operator-** (const [Vector3](#) &in)
- **Vector3 operator*** (double d, const [Vector3](#) &vec)
- **Vector3 operator+** (const [Vector3](#) &vec0, const [Vector3](#) &vec1)
- **Vector3 operator-** (const [Vector3](#) &vec0, const [Vector3](#) &vec1)
- int [getLicenseState](#) ()
- Check the license state.*
- void [printLicense](#) ()
- Print license details.*
- bool [isPure](#) ()
- Check if pure or lm build.*
- bool [activateWof](#) (const char *key, bool bSystemWide)
- Activate WOF license.*
- bool [deactivateWof](#) ()
- Deactivate WOF license.*
- bool [extendTrial](#) (const char *key)
- Extend Trial.*
- void [printVersion](#) ()
- Print version number.*
- void [getVersion](#) (int &versionMajor, int &versionMinor)
- Get version numbers.*
- bool [isRelease](#) ()
- Check if the present binary is a Release or Debug build.*
- [MeshPtr melt](#) (std::vector< [Point3](#) > &vInputCorners, double avgLength, double featureThresh=15.0)
- Remesh (melt) a triangle mesh.*
- [MeshPtr reconstruct_auto](#) (std::vector< [Point3](#) > &vPoints, double sfactor=2.0, int numGrowSteps=10)
- Reconstruct with an automatic spacing value.*
- [MeshPtr reconstruct_abs](#) (std::vector< [Point3](#) > &vPoints, double spacingAbs, int numGrowSteps=10)
- Reconstruct with an absolute spacing value.*
- void [toCloud](#) (std::vector< [Point3](#) > &vCornersIn, double length, double featureThresh, std::vector< [Point3](#) > &vCloudOut)
- Mesh-to-Cloud.*
- void [edgeFlips](#) ([MeshPtr](#) pMesh)
- Flip edges.*
- void [edgeFlipsSimA](#) ([MeshPtr](#) pMesh)
- Flip edges - simulated annealing.*
- void [laplacianSmoothing](#) ([MeshPtr](#) pMesh, int numIterations)
- Laplacian smoothing.*
- int [reduce](#) ([MeshPtr](#) pMesh, double targetLen=DBL_MAX, double maxDev=2.0)
- Reduce.*
- void [autoOffset](#) (std::vector< [Point3](#) > &vPoints, double &xoff, double &yoff, double &zoff)
- Automatic offset.*
- void [subscribe](#) ([ProgressBase](#) *pProgressBase)
- Subscribe to progress updates.*
- [FileType](#) [getFileType](#) (const std::string &filename)
- Get File Type.*
- bool [writePoints_ASCII](#) (const char *filename, const std::vector< [Point3](#) > &vPoints)
- Write points to an ASCII file.*
- bool [writePoints_BIN](#) (const char *filename, std::vector< [Point3](#) > &vPoints)
- Write points to a binary file.*
- bool [readPly](#) (const char *filename, bool bReadPoints, std::vector< [Point3](#) > &vPointsOut)

*Write points to a *.ply file.*

- bool **writePointsPly** (const std::string &filename, std::vector< [GEOM_WOF::Point3](#) > &vPoints, bool bASCII)
- bool **readPoints_ASCII** (const char *filename, std::vector< [Point3](#) > &vPoints)

Read points from an ASCII file.

- bool **readPoints_BIN** (const char *filename, std::vector< [Point3](#) > &vPointsOut)

Read points from a binary file.

- bool **readSTL_ASCII** (const char *filename, std::vector< [Point3](#) > &vTriangleCorners)

Read a mesh from ASCII STL.

- bool **readPoints_auto** (std::string &inFilename, std::vector< [Point3](#) > &vPoints)

Read points from a file (automatic detection)

- bool **writePoints_auto** (std::string &outFilename, std::vector< [Point3](#) > &vPoints, bool bASCII)

Write points to a file.

- bool **writeMesh_auto** (const std::string &filename, std::shared_ptr< [Mesh](#) > pMesh, bool bASCII)

Write mesh to a file.

8.1.1 Detailed Description

Namespace [GEOM_WOF](#)

Namespace of the WOF library

8.1.2 Typedef Documentation

8.1.2.1 MeshPtr typedef std::shared_ptr<[Mesh](#)> [GEOM_WOF::MeshPtr](#)

MeshPtr is a shared pointer to [Mesh](#)

8.1.3 Function Documentation

8.1.3.1 autoOffset() void [GEOM_WOF::autoOffset](#) (
 std::vector< [Point3](#) > & vPoints,
 double & xoff,
 double & yoff,
 double & zoff)

This function moves the center of the point cloud to the origin. This is beneficial for large coordinates because computations can then be carried out with the best possible accuracy. But it's also useful for output formats supporting only 32 bits like STL.

Parameters

in, out	<i>vPoints</i>	are the points to be transformed
out	<i>xoff,yoff,zoff</i>	are used to return the applied offsets

8.1.3.2 subscribe() void [GEOM_WOF::subscribe](#) (
 [ProgressBase](#) * pProgressBase)

You can provide your own progress receiver class (e.g. progress bar) deriving from [ProgressBase](#). Whenever the progress state changes its update method [ProgressBase::update\(\)](#) will be called.

9 Class Documentation

9.1 GEOM_WOF::Mesh Class Reference

3D [Mesh](#) class

```
#include <Mesh.h>
```

Public Member Functions

- [Mesh](#) (RMesh *pRMesh)
Constructor.
- [~Mesh](#) ()
Destructor.
- **Mesh** (const [Mesh](#) &)=delete
- [Mesh](#) & **operator=** (const [Mesh](#) &)=delete
- size_t [getNumT](#) () const
Get the number of triangles.
- void [getTriangles](#) (std::vector< [Point3](#) * > &vTriangleCorners) const
Get Triangles.
- void [getPoints](#) (std::vector< [Point3](#) * > &vPoints) const
Get Points.
- void [contrastSpread](#) (double lowerSkipFrac=.01, double upperSkipFrac=.01)
Get the [Mesh](#) as Vertices and Indices.
- void [colorizeFilledHoles](#) ()
Colorize filled holes.
- void [getVertexIndexData](#) (std::vector< [Point3](#) * > &vVertices, std::vector< int > &vCornerIndices) const
- bool [writePly_BIN](#) (const std::string &name) const
Write Ply (Binary)
- bool [writePly_ASCII](#) (const std::string &name) const
Write Ply (ASCII)
- bool [writeGeomview_ASCII](#) (const std::string &name) const
Write Geomview.
- bool [writeStl_ASCII](#) (const std::string &name) const
Write STL (ASCII)
- void [printStats](#) (const std::string &name) const
Print Statistics.
- double [getAverageEdgeLength](#) () const
Get the average edge length.

9.1.1 Detailed Description

The [Mesh](#) is a 3D triangle mesh.

9.1.2 Member Function Documentation

9.1.2.1 [colorizeFilledHoles\(\)](#) void GEOM_WOF::Mesh::colorizeFilledHoles ()

Vertices in filled holes are by default black. Approximate colors from the hole boundaries.

9.1.2.2 [contrastSpread\(\)](#) void GEOM_WOF::Mesh::contrastSpread (

```
double lowerSkipFrac = .01,  
double upperSkipFrac = .01 )
```

Parameters

<i>vVertices</i>	[out] The vertices of the Mesh
<i>vCornerIndices</i>	[out] Three subsequent indices for each triangle. The indices refer to points in <i>vVertices</i> and thus the index range starts with 0.

Note

There are file formats (e.g., *.obj) where the first index must be 1, not 0! Simply increment the indices by 1 then.

Contrast spreading
RGB contrast spreading.

Parameters

<i>lowerSkipFrac</i>	is by default 0.01 which means the lower 1 % of all values is set to 0.
<i>upperSkipFrac</i>	is by default 0.01 which means the upper 1 % of all values is set to 255.

9.1.2.3 getAverageEdgeLength() `double GEOM_WOF::Mesh::getAverageEdgeLength () const`
Computes and returns the average edge length

9.1.2.4 getPoints() `void GEOM_WOF::Mesh::getPoints (
std::vector< Point3 * > & vPoints) const`

Parameters

out	<i>vPoints</i>	is used to return the vertex pointers
-----	----------------	---------------------------------------

9.1.2.5 getTriangles() `void GEOM_WOF::Mesh::getTriangles (
std::vector< Point3 * > & vTriangleCorners) const`

Parameters

out	<i>vTriangleCorners</i>	is used to return the triangles as 3 vertex pointers per triangle. The order of the corners per triangle is counterclockwise.
-----	-------------------------	---

9.1.2.6 printStatistics() `void GEOM_WOF::Mesh::printStatistics (
const std::string & name) const`
Prints mesh statistics to stdout

Parameters

<i>name</i>	serves as arbitrary identifier that is also printed to stdout
-------------	---

9.1.2.7 writeGeomview_ASCII() `bool GEOM_WOF::Mesh::writeGeomview_ASCII (
const std::string & name) const`

Writes a file for the Geomview viewer

Parameters

<i>name</i>	[in] is the output filename.
-------------	------------------------------

9.1.2.8 writePly_ASCII() `bool GEOM_WOF::Mesh::writePly_ASCII (`
`const std::string & name) const`

Writes an ASCII PLY file

Parameters

<i>name</i>	[in] is the output filename.
-------------	------------------------------

9.1.2.9 writePly_BIN() `bool GEOM_WOF::Mesh::writePly_BIN (`
`const std::string & name) const`

Writes a binary PLY file

Parameters

<i>name</i>	[in] is the output filename.
-------------	------------------------------

9.1.2.10 writeStl_ASCII() `bool GEOM_WOF::Mesh::writeStl_ASCII (`
`const std::string & name) const`

Writes an ASCII STL file

Parameters

<i>name</i>	[in] is the output filename.
-------------	------------------------------

The documentation for this class was generated from the following file:

- Mesh.h

9.2 GEOM_WOF::Point3 Class Reference

3D Point

```
#include <Point3.h>
```

Public Member Functions

- [Point3](#) (const double x_, const double y_, const double z_)
Constructor without color.
- [Point3](#) (const double x_, const double y_, const double z_, unsigned char r_, unsigned char g_, unsigned char b_, unsigned char a_)
Constructor with color.
- [Point3](#) ()
Default constructor.
- [Point3](#) (const [Point3](#) &p_)
Copy constructor.

- `Point3 & operator= (const Point3 &other)`
operator=
- `~Point3 ()`
Destructor.
- `void setColor (unsigned char r_, unsigned char g_, unsigned char b_, unsigned char a_)`
Set color.
- `void getColor_255 (unsigned char &r_, unsigned char &g_, unsigned char &b_, unsigned char &a_) const`
Get color (unsigned char, range=0, ..., 255)
- `void getColor_255 (float &r_, float &g_, float &b_, float &a_) const`
Get color (float, range=0, ..., 255)
- `std::string getColorString ()`
Get color string (string, range=0.0, ..., 1.0)
- `void getColor_1 (float &r_, float &g_, float &b_, float &a_) const`
Get color (float, range=0.0, ..., 1.0)
- `bool hasColor () const`
Has color.
- `double x () const`
Get the x-coordinate.
- `double y () const`
Get the y-coordinate.
- `double z () const`
Get the z-coordinate.
- `void xyz (double &x_, double &y_, double &z_) const`
Get the x-, y- and z-coordinate.
- `void addOwnCoords (double &x, double &y, double &z) const`
Add the point's coordinates to x,y,z.
- `void copyColorFrom (const Point3 &other)`
Copy the color from another point.
- `void copyColorFrom (const Point3 &other0, const Point3 &other1)`
Copy the average color from two points.
- `void addWeightedOwnCoords (double weight, double &x, double &y, double &z) const`
Add the point's weighted coordinates to x,y,z.
- `bool operator< (const Point3 &p) const`
Less than operator.
- `bool operator> (const Point3 &p) const`
Greater than operator.
- `bool operator== (const Point3 &p) const`
Equality operator.
- `bool operator!= (const Point3 &p) const`
Inequality operator.
- `void set (const double x_, const double y_, const double z_)`
Set the coordiantes.
- `void set (const Point3 &pnt)`
Set the coordiantes.
- `Vector3 operator- (const Point3 &other) const`
operator-
- `Point3 operator+ (const Vector3 &vec) const`
operator+
- `Point3 operator- (const Vector3 &vec) const`
operator-

Protected Attributes

- double **coordX**
- double **coordY**
- double **coordZ**
- unsigned char **r**
- unsigned char **g**
- unsigned char **b**
- unsigned char **a**
- bool **bHasColor**

Friends

- std::ostream & **operator**<< (std::ostream &stream, const [Point3](#) &pnt)
- std::istream & **operator**>> (std::istream &stream, [Point3](#) &pnt)

9.2.1 Constructor & Destructor Documentation

9.2.1.1 Point3() [1/4] GEOM_WOF::Point3::Point3 (
const double x_,
const double y_,
const double z_) [inline]

Parameters

x_,y_↔ ,z_	[in] coordinates
---------------	------------------

9.2.1.2 Point3() [2/4] GEOM_WOF::Point3::Point3 (
const double x_,
const double y_,
const double z_,
unsigned char r_,
unsigned char g_,
unsigned char b_,
unsigned char a_) [inline]

Parameters

x_,y_,z_	[in] coordinates
r_,g_,b_↔ ,a_	[in] color

9.2.1.3 Point3() [3/4] GEOM_WOF::Point3::Point3 () [inline]
Coordinates are initialized to 0.

9.2.1.4 Point3() [4/4] GEOM_WOF::Point3::Point3 (
const [Point3](#) & p_) [inline]
Copies the coordinates of p_

9.2.2 Member Function Documentation

9.2.2.1 addOwnCoords() `void GEOM_WOF::Point3::addOwnCoords (`
`double & x,`
`double & y,`
`double & z) const [inline]`

Parameters

<i>x,y,z</i>	[inout] are used to accumulate the point's coordinates
--------------	--

9.2.2.2 addWeightedOwnCoords() `void GEOM_WOF::Point3::addWeightedOwnCoords (`
`double weight,`
`double & x,`
`double & y,`
`double & z) const [inline]`

Parameters

<i>weight</i>	is a factor on x,y,z
<i>x,y,z</i>	[inout] are used to accumulate the point's coordinates

9.2.2.3 copyColorFrom() [1/2] `void GEOM_WOF::Point3::copyColorFrom (`
`const Point3 & other) [inline]`

Parameters

<i>other</i>	[in] is the point whose color is copied
--------------	---

9.2.2.4 copyColorFrom() [2/2] `void GEOM_WOF::Point3::copyColorFrom (`
`const Point3 & other0,`
`const Point3 & other1) [inline]`

Parameters

<i>other0,other1</i>	[in] are the points whose color is averaged
----------------------	---

9.2.2.5 getColor_1() `void GEOM_WOF::Point3::getColor_1 (`
`float & r_,`
`float & g_,`
`float & b_,`
`float & a_) const [inline]`

Parameters

<i>r_,g_,b_↔ ,a_</i>	are red, green, blue, alpha
--------------------------	-----------------------------

9.2.2.6 getColor_255() [1/2] `void GEOM_WOF::Point3::getColor_255 (`
`float & r_,`
`float & g_,`
`float & b_,`
`float & a_) const [inline]`

Parameters

<code>r_,g_,b_,a_</code>	are red, green, blue, alpha
--------------------------	-----------------------------

9.2.2.7 getColor_255() [2/2] `void GEOM_WOF::Point3::getColor_255 (`
`unsigned char & r_,`
`unsigned char & g_,`
`unsigned char & b_,`
`unsigned char & a_) const [inline]`

Parameters

<code>r_,g_,b_,a_</code>	are red, green, blue, alpha
--------------------------	-----------------------------

9.2.2.8 getColorString() `std::string GEOM_WOF::Point3::getColorString () [inline]`

Parameters

<code>r_,g_,b_,a_</code>	are red, green, blue, alpha
--------------------------	-----------------------------

9.2.2.9 hasColor() `bool GEOM_WOF::Point3::hasColor () const [inline]`
Returns whether a color has been assigned to the point

9.2.2.10 operator"!="() `bool GEOM_WOF::Point3::operator!= (`
`const Point3 & p) const [inline]`

Parameters

<code>p</code>	[in] The point whose coordinates are compared with the ones of the present point
----------------	--

9.2.2.11 operator+() `Point3 GEOM_WOF::Point3::operator+ (`
`const Vector3 & vec) const [inline]`

Returns

a point that corresponds to the present point moved by `vec`

9.2.2.12 operator-() [1/2] `Vector3 GEOM_WOF::Point3::operator- (`
`const Point3 & other) const [inline]`

Returns

the difference vector (`*this - other`) i.e., a vector pointing from the point `other` to `*this`.

9.2.2.13 operator-() [2/2] `Point3 GEOM_WOF::Point3::operator- (`
`const Vector3 & vec) const [inline]`

Returns

a point that corresponds to the present point moved by `vec`

9.2.2.14 operator<() `bool GEOM_WOF::Point3::operator< (`
`const Point3 & p) const [inline]`

Parameters

<code>p</code>	[in] is compared with <code>*this</code>
----------------	--

Returns

true if the coordinates of the present point are lexicographically smaller than the ones of `p` or false otherwise

9.2.2.15 operator=() `Point3& GEOM_WOF::Point3::operator= (`
`const Point3 & other) [inline]`

Assigns `other`

9.2.2.16 operator==() `bool GEOM_WOF::Point3::operator== (`
`const Point3 & p) const [inline]`

Parameters

<code>p</code>	[in] The point whose coordinates are compared with the ones of the present point
----------------	--

9.2.2.17 operator>() `bool GEOM_WOF::Point3::operator> (`
`const Point3 & p) const [inline]`

Parameters

<code>p</code>	[in] The point whose coordinates are compared with the ones of the present point
----------------	--

Returns

true if the coordinates of the present point are lexicographically greater than the ones of `p` or false otherwise

9.2.2.18 set() [1/2] `void GEOM_WOF::Point3::set (`
`const double x_,`

```
const double y_,
const double z_ ) [inline]
```

Set the coordinates of the present point to $x_y_z_$.

Parameters

$x_y_z_$	[in] are the coordinates to be assigned
-------------	---

```
9.2.2.19 set() [2/2] void GEOM_WOF::Point3::set (
const Point3 & pnt ) [inline]
```

Set the coordinates of the present point to the ones of pnt

Parameters

<i>pnt</i>	carries the coordinates to be assigned
------------	--

```
9.2.2.20 setColor() void GEOM_WOF::Point3::setColor (
unsigned char r_,
unsigned char g_,
unsigned char b_,
unsigned char a_ ) [inline]
```

Parameters

$r_g_b_a_$	are red, green, blue, alpha in the range 0-255
----------------	--

```
9.2.2.21 x() double GEOM_WOF::Point3::x ( ) const [inline]
```

Returns

the x-coordinate

```
9.2.2.22 xyz() void GEOM_WOF::Point3::xyz (
double & x_,
double & y_,
double & z_ ) const [inline]
```

Parameters

$x_y_z_$	[out] x,y,z-coordinates
-------------	-------------------------

Returns

all 3 coordinates at once

9.2.2.23 `y()` `double GEOM_WOF::Point3::y () const [inline]`

Returns

the y-coordinate

9.2.2.24 `z()` `double GEOM_WOF::Point3::z () const [inline]`

Returns

the z-coordinate

The documentation for this class was generated from the following file:

- [Point3.h](#)

9.3 GEOM_WOF::ProgressBase Class Reference

Base class for progress subscribers.

```
#include <wof_api_definitions.h>
```

Public Member Functions

- virtual void [update](#) (const std::string &s, double d)=0
update

9.3.1 Detailed Description

A progress subscriber class can be derived from [ProgressBase](#) to receive progress updates from the WOF library. A simple terminal progress bar could be derived like this:

```
class MyProgressBar:public GEOM_WOF::ProgressBase
{
public:
    // WOF calls the update method with d={0.0,...,1.0}
    void update(const std::string& s,double d)
    {
        if(s!=lastMessage)
        {
            cout<<"\n"; // New message, line feed
            lastMessage=s;
        }
        cout<<("Progress(\""+s+"\"): ")<<d*100.0<<" %
        if(d>=1.0) cout<<endl;
        \r"<<flush;
    }
protected:
    std::string lastMessage;
};
```

9.3.2 Member Function Documentation

9.3.2.1 `update()` `virtual void GEOM_WOF::ProgressBase::update (`
`const std::string & s,`
`double d) [pure virtual]`

This method must be defined in the derived class. It is called whenever the progress changes and thus it should be computationally inexpensive.

The documentation for this class was generated from the following file:

- [wof_api_definitions.h](#)

9.4 GEOM_WOF::TimerC Class Reference

Timer class.

```
#include <TimerC.h>
```

Public Member Functions

- [TimerC](#) ()
Constructor.
- double [stop](#) ()
Timer stop.
- double [get](#) () const
Get the elapsed time.
- double [getSecondsSinceLastReport](#) ()
Get elapsed time since last report.
- void [report](#) (const std::string &s)
Report.

9.4.1 Detailed Description

[TimerC](#) measures the time consumption

9.4.2 Constructor & Destructor Documentation

9.4.2.1 [TimerC\(\)](#) `GEOM_WOF::TimerC::TimerC () [inline]`

At construction [TimerC](#) stores the current time

9.4.3 Member Function Documentation

9.4.3.1 [get\(\)](#) `double GEOM_WOF::TimerC::get () const [inline]`

Returns

the elapsed time in seconds between [TimerC](#) construction and the first call to [TimerC::stop\(\)](#). When the timer has not been stopped then the time since construction is returned.

9.4.3.2 [getSecondsSinceLastReport\(\)](#) `double GEOM_WOF::TimerC::getSecondsSinceLastReport () [inline]`

Returns the elapsed seconds since last report (if none, since construction)

9.4.3.3 [report\(\)](#) `void GEOM_WOF::TimerC::report (const std::string & s) [inline]`

Prints the time since last report (or, if none, since construction). This command is intended to measure successive intervals

9.4.3.4 [stop\(\)](#) `double GEOM_WOF::TimerC::stop () [inline]`

Returns

the elapsed time since [TimerC](#) construction in seconds

The documentation for this class was generated from the following file:

- [TimerC.h](#)

9.5 GEOM_WOF::Vector3 Class Reference

3D Vector

```
#include <Vector3.h>
```

Public Member Functions

- **Vector3** (const double x_, const double y_, const double z_)
Constructor.
- **Vector3** ()
Default constructor.
- **Vector3** (const **Vector3** &v_)
Copy constructor.
- bool **isDegenerate** () const
isDegenerate
- void **xyz** (double &x_, double &y_, double &z_) const
Get x,y,z.
- void **reset** ()
reset
- double **x** () const
Get the x-value.
- double **y** () const
Get the y-value.
- double **z** () const
Get the z-value.
- void **set** (const double x_, const double y_, const double z_)
Set x,y,z.
- void **add** (const **Vector3** &other)
Add a Vector3 to the present one.
- void **sub** (const **Vector3** &other)
- void **div** (double div)
- void **mul** (double mul)
- double **sqLength** () const
Get the squared length of the vector.
- int **getMaxAbsIndex** () const
Get max index.
- double **getMaxComponent** () const
Get max component.
- double **getMaxAbsComponent** () const
Get max absolute component.
- double **getCartesian** (int i) const
Get component i.
- double **length** () const
Get the length of the vector.
- double **operator*** (const **Vector3** &other) const
Scalar product.
- **Vector3 operator*** (double val) const
Multiply by a scalar value.
- **Vector3 operator/** (double val) const
Divide by a scalar value.
- **Vector3 & operator=** (const **Vector3** &other)
Assignment operator.
- **Vector3 & operator+=** (const **Vector3** &other)
- **Vector3 & operator-=** (const **Vector3** &other)
- **Vector3 & operator/=** (double div)
- **Vector3 & operator*=** (double mul)

Protected Attributes

- double **valX**
- double **valY**
- double **valZ**

9.5.1 Constructor & Destructor Documentation

9.5.1.1 Vector3() [1/3] `GEOM_WOF::Vector3::Vector3 (`
`const double x_,`
`const double y_,`
`const double z_)`

Parameters

$x_, y_ \leftrightarrow$ $z_$	Values to initialize the Vector
----------------------------------	---------------------------------

9.5.1.2 Vector3() [2/3] `GEOM_WOF::Vector3::Vector3 ()`
The vector is initialized to (0,0,0)

9.5.1.3 Vector3() [3/3] `GEOM_WOF::Vector3::Vector3 (`
`const Vector3 & v_)`
Copies `v_`

9.5.2 Member Function Documentation

9.5.2.1 add() `void GEOM_WOF::Vector3::add (`
`const Vector3 & other) [inline]`

Parameters

<i>other</i>	is added to the present Vector3
--------------	---

9.5.2.2 getCartesian() `double GEOM_WOF::Vector3::getCartesian (`
`int i) const`

Returns

the `i`-th component

9.5.2.3 getMaxAbsComponent() `double GEOM_WOF::Vector3::getMaxAbsComponent () const`

Returns

the maximum absolute component

9.5.2.4 getMaxAbsIndex() `int GEOM_WOF::Vector3::getMaxAbsIndex () const`

Returns

the index of the largest absolute component (0,1 or 2)

9.5.2.5 getMaxComponent() `double GEOM_WOF::Vector3::getMaxComponent () const [inline]`

Returns

the maximum component

9.5.2.6 isDegenerate() `bool GEOM_WOF::Vector3::isDegenerate () const [inline]`

Returns

true if the vector length is 0, false otherwise.

9.5.2.7 length() `double GEOM_WOF::Vector3::length () const`

Returns

the length of the vector

9.5.2.8 operator*() [1/2] `double GEOM_WOF::Vector3::operator* (const Vector3 & other) const`

Returns

the scalar product of the present [Vector3](#) and other

9.5.2.9 operator*() [2/2] `Vector3 GEOM_WOF::Vector3::operator* (double val) const`

Returns

the present [Vector3](#) multiplied by val

9.5.2.10 operator/() `Vector3 GEOM_WOF::Vector3::operator/ (double val) const`

Returns

the present [Vector3](#) divided by val

9.5.2.11 reset() `void GEOM_WOF::Vector3::reset () [inline]`
Set the vector to (0,0,0)

9.5.2.12 set() `void GEOM_WOF::Vector3::set (const double x_, const double y_, const double z_)`

Assigns values to the present [Vector3](#)

Parameters

$x_y_z_$	Values to assign
-------------	------------------

9.5.2.13 sqLength() `double GEOM_WOF::Vector3::sqLength () const`

Returns

the squared length of the [Vector3](#)

9.5.2.14 x() `double GEOM_WOF::Vector3::x () const [inline]`

Returns

x

9.5.2.15 xyz() `void GEOM_WOF::Vector3::xyz (double & x_, double & y_, double & z_) const [inline]`

Parameters

$x_y_z_$	[out] Used to return the x,y,z-values of the Vector
-------------	---

9.5.2.16 y() `double GEOM_WOF::Vector3::y () const [inline]`

Returns

y

9.5.2.17 z() `double GEOM_WOF::Vector3::z () const [inline]`

Returns

z

The documentation for this class was generated from the following file:

- Vector3.h

9.6 GEOM_WOF::WofBugException Struct Reference

Bug-Exception.

```
#include <wof_api_definitions.h>
```

Inherits `std::exception`.

Public Member Functions

- virtual const char * **what** () const throw ()

9.6.1 Detailed Description

The [WofBugException](#) is thrown in case of unexpected states caused by invalid input **OR** a bug. Software quality is very important for this project. If you find a bug, send a bug report and it will be processed immediately.

The documentation for this struct was generated from the following file:

- [wof_api_definitions.h](#)

9.7 GEOM_WOF::WofLicenseException Class Reference

License-Exception.

```
#include <wof_api_definitions.h>
```

Inherits `std::exception`.

9.7.1 Detailed Description

The [WofLicenseException](#) is thrown in case of an invalid license state. If your trial has expired but you still need the software for your non-commercial research, contact Geom Software: bkorn@geom.at for a trial extension code. Include information about your project.

The documentation for this class was generated from the following file:

- [wof_api_definitions.h](#)

10 File Documentation

10.1 wof_api.h File Reference

```
#include <vector>
#include "License.h"
#include "wof_api_io.h"
#include "wof_api_functions.h"
#include "wof_api_definitions.h"
#include "TimerC.h"
```

Namespace

- [GEOM_WOF](#)

Macros

- `#define WOFLIC_ACTIVATED 10`
- `#define WOFLIC_GRACE_OK 11`
- `#define WOFLIC_GRACE_EXPIRED 12`
- `#define WOFLIC_TRIAL 13`
- `#define WOFLIC_INVALID 14`
- `#define WOFLIC_PURE 15`

Functions

- `int GEOM_WOF::getLicenseState ()`
Check the license state.
- `void GEOM_WOF::printLicense ()`
Print license details.
- `bool GEOM_WOF::isPure ()`
Check if pure or lm build.
- `bool GEOM_WOF::activateWof (const char *key, bool bSystemWide)`
Activate WOF license.

- bool [GEOM_WOF::deactivateWof](#) ()
Deactivate WOF license.
- bool [GEOM_WOF::extendTrial](#) (const char *key)
Extend Trial.
- void [GEOM_WOF::printVersion](#) ()
Print version number.
- void [GEOM_WOF::getVersion](#) (int &versionMajor, int &versionMinor)
Get version numbers.
- bool [GEOM_WOF::isRelease](#) ()
Check if the present binary is a Release or Debug build.

10.2 wof_api_definitions.h File Reference

Classes

- class [GEOM_WOF::WofLicenseException](#)
License-Exception.
- struct [GEOM_WOF::WofBugException](#)
Bug-Exception.
- class [GEOM_WOF::ProgressBase](#)
Base class for progress subscribers.

Namespace

- [GEOM_WOF](#)

Macros

- #define **WOF_VER_MAJOR** 1
- #define **WOF_VER_MINOR** 16
- #define **CLASS_DECLSPEC**

10.3 wof_api_functions.h File Reference

```
#include <vector>
#include <float.h>
#include "Point3.h"
#include "Mesh.h"
```

Namespace

- [GEOM_WOF](#)

Functions

- MeshPtr [GEOM_WOF::melt](#) (std::vector< Point3 > &vInputCorners, double avgLength, double feature↔
Thresh=15.0)
Remesh (melt) a triangle mesh.
- MeshPtr [GEOM_WOF::reconstruct_auto](#) (std::vector< Point3 > &vPoints, double sfactor=2.0, int numGrow↔
Steps=10)
Reconstruct with an automatic spacing value.
- MeshPtr [GEOM_WOF::reconstruct_abs](#) (std::vector< Point3 > &vPoints, double spacingAbs, int numGrow↔
Steps=10)
Reconstruct with an absolute spacing value.

- void [GEOM_WOF::toCloud](#) (std::vector< Point3 > &vCornersIn, double length, double featureThresh, std::vector< Point3 > &vCloudOut)
Mesh-to-Cloud.
- void [GEOM_WOF::edgeFlips](#) (MeshPtr pMesh)
Flip edges.
- void [GEOM_WOF::edgeFlipsSimA](#) (MeshPtr pMesh)
Flip edges - simulated annealing.
- void [GEOM_WOF::laplacianSmoothing](#) (MeshPtr pMesh, int numIterations)
Laplacian smoothing.
- int [GEOM_WOF::reduce](#) (MeshPtr pMesh, double targetLen=DBL_MAX, double maxDev=2.0)
Reduce.
- void [GEOM_WOF::autoOffset](#) (std::vector< Point3 > &vPoints, double &xoff, double &yoff, double &zoff)
Automatic offset.
- void [GEOM_WOF::subscribe](#) (ProgressBase *pProgressBase)
Subscribe to progress updates.

10.4 wof_api_io.h File Reference

```
#include <vector>
#include "Point3.h"
#include "Mesh.h"
```

Namespace

- [GEOM_WOF](#)

Enumerations

- enum [GEOM_WOF::FileType](#) {
[GEOM_WOF::FT_STL](#) , [GEOM_WOF::FT_PLY](#) , [GEOM_WOF::FT_XYZ](#) , [GEOM_WOF::FT_BIN](#) ,
[GEOM_WOF::FT_LIST](#) , [GEOM_WOF::FT_UNKNOWN](#) }
Filetype.

Functions

- FileType [GEOM_WOF::getFileType](#) (const std::string &filename)
Get File Type.
- bool [GEOM_WOF::writePoints_ASCII](#) (const char *filename, const std::vector< Point3 > &vPoints)
Write points to an ASCII file.
- bool [GEOM_WOF::writePoints_BIN](#) (const char *filename, std::vector< Point3 > &vPoints)
Write points to a binary file.
- bool [GEOM_WOF::readPly](#) (const char *filename, bool bReadPoints, std::vector< Point3 > &vPointsOut)
*Write points to a *.ply file.*
- bool [GEOM_WOF::writePointsPly](#) (const std::string &filename, std::vector< [GEOM_WOF::Point3](#) > &vPoints, bool bASCII)
- bool [GEOM_WOF::readPoints_ASCII](#) (const char *filename, std::vector< Point3 > &vPoints)
Read points from an ASCII file.
- bool [GEOM_WOF::readPoints_BIN](#) (const char *filename, std::vector< Point3 > &vPointsOut)
Read points from a binary file.
- bool [GEOM_WOF::readSTL_ASCII](#) (const char *filename, std::vector< Point3 > &vTriangleCorners)
Read a mesh from ASCII STL.
- bool [GEOM_WOF::readPoints_auto](#) (std::string &inFilename, std::vector< Point3 > &vPoints)
Read points from a file (automatic detection)

- bool [GEOM_WOF::writePoints_auto](#) (std::string &outFilename, std::vector< Point3 > &vPoints, bool bASCII)
Write points to a file.
- bool [GEOM_WOF::writeMesh_auto](#) (const std::string &filename, std::shared_ptr< Mesh > pMesh, bool bASCII)
Write mesh to a file.

Index

- activateWof
 - License related functions, [6](#)
- add
 - GEOM_WOF::Vector3, [31](#)
- addOwnCoords
 - GEOM_WOF::Point3, [24](#)
- addWeightedOwnCoords
 - GEOM_WOF::Point3, [24](#)
- autoOffset
 - GEOM_WOF, [18](#)
- colorizeFilledHoles
 - GEOM_WOF::Mesh, [19](#)
- contrastSpread
 - GEOM_WOF::Mesh, [19](#)
- copyColorFrom
 - GEOM_WOF::Point3, [24](#)
- deactivateWof
 - License related functions, [7](#)
- edgeFlips
 - Geometry functions, [9](#)
- edgeFlipsSimA
 - Geometry functions, [9](#)
- extendTrial
 - License related functions, [7](#)
- File I/O, [11](#)
 - FileType, [12](#)
 - FT_BIN, [12](#)
 - FT_LIST, [12](#)
 - FT_PLY, [12](#)
 - FT_STL, [12](#)
 - FT_UNKNOWN, [12](#)
 - FT_XYZ, [12](#)
 - getFileType, [12](#)
 - readPly, [12](#)
 - readPoints_ASCII, [13](#)
 - readPoints_auto, [13](#)
 - readPoints_BIN, [14](#)
 - readSTL_ASCII, [14](#)
 - writeMesh_auto, [14](#)
 - writePoints_ASCII, [15](#)
 - writePoints_auto, [15](#)
 - writePoints_BIN, [15](#)
- FileType
 - File I/O, [12](#)
- FT_BIN
 - File I/O, [12](#)
- FT_LIST
 - File I/O, [12](#)
- FT_PLY
 - File I/O, [12](#)
- FT_STL
 - File I/O, [12](#)

- FT_UNKNOWN
 - File I/O, [12](#)
- FT_XYZ
 - File I/O, [12](#)
- GEOM_WOF, [16](#)
 - autoOffset, [18](#)
 - MeshPtr, [18](#)
 - subscribe, [18](#)
- GEOM_WOF::Mesh, [19](#)
 - colorizeFilledHoles, [19](#)
 - contrastSpread, [19](#)
 - getAverageEdgeLength, [20](#)
 - getPoints, [20](#)
 - getTriangles, [20](#)
 - printStatistics, [20](#)
 - writeGeomview_ASCII, [20](#)
 - writePly_ASCII, [21](#)
 - writePly_BIN, [21](#)
 - writeStl_ASCII, [21](#)
- GEOM_WOF::Point3, [21](#)
 - addOwnCoords, [24](#)
 - addWeightedOwnCoords, [24](#)
 - copyColorFrom, [24](#)
 - getColor_1, [24](#)
 - getColor_255, [25](#)
 - getColorString, [25](#)
 - hasColor, [25](#)
 - operator!=, [25](#)
 - operator<, [26](#)
 - operator>, [26](#)
 - operator+, [25](#)
 - operator-, [25, 26](#)
 - operator=, [26](#)
 - operator==, [26](#)
 - Point3, [23](#)
 - set, [26, 27](#)
 - setColor, [27](#)
 - x, [27](#)
 - xyz, [27](#)
 - y, [27](#)
 - z, [28](#)
- GEOM_WOF::ProgressBase, [28](#)
 - update, [28](#)
- GEOM_WOF::TimerC, [28](#)
 - get, [29](#)
 - getSecondsSinceLastReport, [29](#)
 - report, [29](#)
 - stop, [29](#)
 - TimerC, [29](#)
- GEOM_WOF::Vector3, [29](#)
 - add, [31](#)
 - getCartesian, [31](#)
 - getMaxAbsComponent, [31](#)
 - getMaxAbsIndex, [31](#)

- getMaxComponent, 32
- isDegenerate, 32
- length, 32
- operator*, 32
- operator/, 32
- reset, 32
- set, 32
- sqLength, 33
- Vector3, 31
- x, 33
- xyz, 33
- y, 33
- z, 33
- GEOM_WOF::WofBugException, 33
- GEOM_WOF::WofLicenseException, 34
- Geometry functions, 8
 - edgeFlips, 9
 - edgeFlipsSimA, 9
 - laplacianSmoothing, 9
 - melt, 9
 - reconstruct_abs, 10
 - reconstruct_auto, 10
 - reduce, 11
 - toCloud, 11
- get
 - GEOM_WOF::TimerC, 29
- getAverageEdgeLength
 - GEOM_WOF::Mesh, 20
- getCartesian
 - GEOM_WOF::Vector3, 31
- getColor_1
 - GEOM_WOF::Point3, 24
- getColor_255
 - GEOM_WOF::Point3, 25
- getColorString
 - GEOM_WOF::Point3, 25
- getFileType
 - File I/O, 12
- getLicenseState
 - License related functions, 7
- getMaxAbsComponent
 - GEOM_WOF::Vector3, 31
- getMaxAbsIndex
 - GEOM_WOF::Vector3, 31
- getMaxComponent
 - GEOM_WOF::Vector3, 32
- getPoints
 - GEOM_WOF::Mesh, 20
- getSecondsSinceLastReport
 - GEOM_WOF::TimerC, 29
- getTriangles
 - GEOM_WOF::Mesh, 20
- getVersion
 - Version related functions, 8
- hasColor
 - GEOM_WOF::Point3, 25
- isDegenerate
 - GEOM_WOF::Vector3, 32
- isRelease
 - Version related functions, 8
- laplacianSmoothing
 - Geometry functions, 9
- length
 - GEOM_WOF::Vector3, 32
- License related functions, 5
 - activateWof, 6
 - deactivateWof, 7
 - extendTrial, 7
 - getLicenseState, 7
 - WOFLIC_ACTIVATED, 6
 - WOFLIC_GRACE_EXPIRED, 6
 - WOFLIC_GRACE_OK, 6
 - WOFLIC_INVALID, 6
 - WOFLIC_PURE, 6
 - WOFLIC_TRIAL, 6
- melt
 - Geometry functions, 9
- MeshPtr
 - GEOM_WOF, 18
- operator!=
 - GEOM_WOF::Point3, 25
- operator<
 - GEOM_WOF::Point3, 26
- operator>
 - GEOM_WOF::Point3, 26
- operator*
 - GEOM_WOF::Vector3, 32
- operator+
 - GEOM_WOF::Point3, 25
- operator-
 - GEOM_WOF::Point3, 25, 26
- operator/
 - GEOM_WOF::Vector3, 32
- operator=
 - GEOM_WOF::Point3, 26
- operator==
 - GEOM_WOF::Point3, 26
- Point3
 - GEOM_WOF::Point3, 23
- printStatistics
 - GEOM_WOF::Mesh, 20
- printVersion
 - Version related functions, 8
- readPly
 - File I/O, 12
- readPoints_ASCII
 - File I/O, 13
- readPoints_auto
 - File I/O, 13
- readPoints_BIN
 - File I/O, 14

- readSTL_ASCII
 - File I/O, [14](#)
- reconstruct_abs
 - Geometry functions, [10](#)
- reconstruct_auto
 - Geometry functions, [10](#)
- reduce
 - Geometry functions, [11](#)
- report
 - GEOM_WOF::TimerC, [29](#)
- reset
 - GEOM_WOF::Vector3, [32](#)
- set
 - GEOM_WOF::Point3, [26, 27](#)
 - GEOM_WOF::Vector3, [32](#)
- setColor
 - GEOM_WOF::Point3, [27](#)
- sqlLength
 - GEOM_WOF::Vector3, [33](#)
- stop
 - GEOM_WOF::TimerC, [29](#)
- subscribe
 - GEOM_WOF, [18](#)
- TimerC
 - GEOM_WOF::TimerC, [29](#)
- toCloud
 - Geometry functions, [11](#)
- update
 - GEOM_WOF::ProgressBase, [28](#)
- Vector3
 - GEOM_WOF::Vector3, [31](#)
- Version related functions, [7](#)
 - getVersion, [8](#)
 - isRelease, [8](#)
 - printVersion, [8](#)
- wof_api.h, [34](#)
- wof_api_definitions.h, [35](#)
- wof_api_functions.h, [35](#)
- wof_api_io.h, [36](#)
- WOFLIC_ACTIVATED
 - License related functions, [6](#)
- WOFLIC_GRACE_EXPIRED
 - License related functions, [6](#)
- WOFLIC_GRACE_OK
 - License related functions, [6](#)
- WOFLIC_INVALID
 - License related functions, [6](#)
- WOFLIC_PURE
 - License related functions, [6](#)
- WOFLIC_TRIAL
 - License related functions, [6](#)
- writeGeomview_ASCII
 - GEOM_WOF::Mesh, [20](#)
- writeMesh_auto
 - File I/O, [14](#)
- writePly_ASCII
 - GEOM_WOF::Mesh, [21](#)
- writePly_BIN
 - GEOM_WOF::Mesh, [21](#)
- writePoints_ASCII
 - File I/O, [15](#)
- writePoints_auto
 - File I/O, [15](#)
- writePoints_BIN
 - File I/O, [15](#)
- writeStl_ASCII
 - GEOM_WOF::Mesh, [21](#)
- x
 - GEOM_WOF::Point3, [27](#)
 - GEOM_WOF::Vector3, [33](#)
- xyz
 - GEOM_WOF::Point3, [27](#)
 - GEOM_WOF::Vector3, [33](#)
- y
 - GEOM_WOF::Point3, [27](#)
 - GEOM_WOF::Vector3, [33](#)
- z
 - GEOM_WOF::Point3, [28](#)
 - GEOM_WOF::Vector3, [33](#)